```
  Type: 'AWS::EC2::RouteTable'
  Properties:
    VpcId: !Ref VPC
RouteTableAssociationPublicNAT:
  Type: 'AWS::EC2::SubnetRouteTableAssociation'
  Properties:
    SubnetId: !Ref SubnetPublicNAT
    RouteTableId: !Ref RouteTablePublicNAT
RoutePublicNATToInternet:                          ②
  Type: 'AWS::EC2::Route'
  Properties:
    RouteTableId: !Ref RouteTablePublicNAT
    DestinationCidrBlock: '0.0.0.0/0'
    GatewayId: !Ref InternetGateway
  DependsOn: VPCGatewayAttachment
NetworkAclPublicNAT:
  Type: 'AWS::EC2::NetworkAcl'
  Properties:
    VpcId: !Ref VPC
SubnetNetworkAclAssociationPublicNAT:
  Type: 'AWS::EC2::SubnetNetworkAclAssociation'
  Properties:
    SubnetId: !Ref SubnetPublicNAT
    NetworkAclId: !Ref NetworkAclPublicNAT
```

① 10.0.0.0/24 is the NAT subnet.

② The NAT subnet is public with a route to the internet.

We need a bunch of NACL rules to make the NAT gateway work.

To allow all VPC subnets to use the NAT gateway for HTTP and HTTPS, perform the following steps:

1. Allow inbound ports 80 (HTTP) and 443 (HTTPS) from 10.0.0.0/16.
2. Allow outbound ephemeral ports to 10.0.0.0/16.

To allow the NAT gateway to reach out to the internet on HTTP and HTTPS, perform these steps:

- Allow outbound ports 80 (HTTP) and 443 (HTTPS) to 0.0.0.0/0.
- Allow inbound ephemeral ports from 0.0.0.0/0.