attributes you need when creating an RDS database instance using CloudFormation or the Management Console.

Table 10.2 Attributes needed to connect to an RDS database

Attribute	Description
`AllocatedStorage`	Storage size of your database in GB
`DBInstanceClass`	Size (also known as instance type) of the underlying virtual machine
`Engine`	Database engine (Aurora, PostgreSQL, MySQL, MariaDB, Oracle Database, or Microsoft SQL Server) you want to use
`DBName`	Identifier for the database
`MasterUsername`	Name for the admin user
`MasterUserPassword`	Password for the admin user

It is possible to configure a database instance as publicly accessible, but we generally do not recommend enabling access from the internet to your database, to prevent unwanted access. Instead, as shown in listing 10.1, an RDS instance should be accessible only within the VPC.

To connect to an RDS database instance, you need an EC2 instance running in the same VPC. First, connect to the EC2 instance. From there, you can then connect to the database instance.

Listing 10.1 Excerpt from the CloudFormation template for setting up an RDS database

```
Resources:
  # [...]
  DatabaseSecurityGroup:                                    ①
    Type: 'AWS::EC2::SecurityGroup'
    Properties:
      GroupDescription: 'awsinaction-db-sg'
```