① The primary key consists of the uid (john) used as the partition key and tid (1) used as the sort key.

② The sort keys are sorted within a partition key.

③ There is no order in the partition keys.

Execute the following command to create the `todo-task` table with a primary key consisting of the partition key `uid` and sort key `tid` like this:

```
$ aws dynamodb create-table --table-name todo-task \
➥ --attribute-definitions AttributeName=uid,AttributeType=S \    ①
➥ AttributeName=tid,AttributeType=N \
➥ --key-schema AttributeName=uid,KeyType=HASH \
➥ AttributeName=tid,KeyType=RANGE \                              ②
➥ --provisioned-throughput ReadCapacityUnits=5,WriteCapacityUnits=5
```

① At least two attributes are needed for a partition key and sort key.

② The tid attribute is the sort key.

Wait until the table status changes to `ACTIVE` when you run `aws dynamodb describe-table --table-name todo-task`.

The `todo-user` and `todo-task` tables are ready. Time to add some data.

12.3 Adding data

Now you have two tables up and running to store users and their tasks. To use them, you need to add data. You'll access DynamoDB via the Node.js SDK, so it's time to set up the SDK and some boilerplate code before you implement adding users and tasks.