			be started based on the launch template.
`AutoScalingGroup`	`VPCZoneIdentifier`	The subnet IDs in which you want to start virtual machines	Any subnet ID from a VPC from your account. Subnets must belong to the same VPC.
`AutoScalingGroup`	`HealthCheckType`	The health check used to identify failed virtual machines. If the health check fails, the Auto Scaling group replaces the virtual machine with a new one.	`EC2` to use the status checks of the virtual machine, or `ELB` to use the health check of the load balancer (see chapter 16).

One important difference exists between the definition of a single EC2 instance and the launch template: the subnet for the virtual machine isn't defined in the launch template but rather in the Auto Scaling group.

An Auto Scaling group is also used if you need to scale the number of virtual machines based on usage of your system. You'll learn how to scale the number of EC2 instances based on current load in chapter 17. In this chapter, you only need to make sure a single virtual machine is always running. Because you need a single virtual machine, set the following parameters for autoscaling to `1`:

- `MinSize`
- `MaxSize`

Listing 13.3 Launching a Jenkins virtual machine with autoscaling in two AZs

```
# [...]
LaunchTemplate:
  Type: 'AWS::EC2::LaunchTemplate'                    ①
```