Listing 15.10 Orchestrating rolling updates with the Auto Scaling group

```
# [...]
AutoScalingGroup:                                    ①
  Type: 'AWS::AutoScaling::AutoScalingGroup'
  Properties:
    TargetGroupARNs:
    - !Ref LoadBalancerTargetGroup
    LaunchTemplate:                                  ②
      LaunchTemplateId: !Ref LaunchTemplate
      Version: !GetAtt 'LaunchTemplate.LatestVersionNumber'
    MinSize: 1                                       ③
    MaxSize: 2                                       ④
    HealthCheckGracePeriod: 300
    HealthCheckType: ELB
    VPCZoneIdentifier:
    - !Ref SubnetA
    - !Ref SubnetB
    Tags:
    - PropagateAtLaunch: true
      Value: etherpad
      Key: Name
  CreationPolicy:
    ResourceSignal:
      Timeout: PT10M
  UpdatePolicy:
    AutoScalingRollingUpdate:                        ⑤
      PauseTime: PT10M                               ⑥
      WaitOnResourceSignals: true                    ⑦
      MinInstancesInService: 1                       ⑧
# [...]
```

① The Auto Scaling group ensures that an EC2 instance is running and is replaced in case of failure.

② References the launch template explained in listing 15.9

③ Starts a single machine, because Etherpad cannot run on multiple machines in parallel

④ During a rolling update, the Auto Scaling group launches a new machine before terminating the old one; therefore, we need to set the maximum size to 2.

⑤ The update policy configures the rolling update.

⑥ The Auto Scaling group will wait 10 minutes for a new EC2 instance signal success with cfn-signal.