```
  Type: 'AWS::EC2::SecurityGroup'
  Properties:
    GroupDescription: 'awsinaction-elb-sg'
    VpcId: !Ref VPC
    SecurityGroupIngress:
    - CidrIp: '0.0.0.0/0'                                    ⑨
      FromPort: 80
      IpProtocol: tcp
      ToPort: 80
```

① The load balancer distributes incoming requests among a fleet of virtual machines.

② Configures a listener for the load balancer

③ The HTTP listener forwards all requests to the default target group defined below.

④ The listener will listen for HTTP requests on port 80/TCP.

⑤ The default target group

⑥ The target group will check the health of registered EC2 instances by sending HTTP requests on port 8080/TCP.

⑦ By default, the target group will forward requests to port 8080/TCP of registered virtual machines.

⑧ A security group for the load balancer

⑨ Allows incoming traffic on port 80/TCP from anywhere

Next, creating an Auto Scaling group to launch EC2 instances and registering them at the load balancer is illustrated in the following listing.

Listing 16.10 CloudFormation template: Auto Scaling group for the Imagery server

```
ServerSecurityGroup:                                         ①
  Type: 'AWS::EC2::SecurityGroup'
  Properties:
    GroupDescription: 'imagery-worker'
    VpcId: !Ref VPC
    SecurityGroupIngress:
    - FromPort: 8080                                         ②
      IpProtocol: tcp
      SourceSecurityGroupId: !Ref LoadBalancerSecurityGroup
      ToPort: 8080
ServerLaunchTemplate:                                        ③
  Type: 'AWS::EC2::LaunchTemplate'
```