Option	Description
`-o, --output <OUTPUT_DIR>`	Output directory in which to place the published artifacts. The default is \bin\Debug\[target framework]\publish.
`-c, --configuration <CONFIGURATION>`	Configuration to use for building the project. The default for web app projects is `Debug`.
`-f, --framework <FRAMEWORK>`	Target framework to publish for. The target framework has to be specified in the project file.
`-r, --runtime <RUNTIME_IDENTIFIER>`	Publish the project for a given runtime. The default is to publish a framework-dependent app targeting the current operating system.
`--self-contained`	Publish the .NET Core runtime with your application, so the runtime doesn't need to be installed on the target machine. It defaults to `true` if a runtime identifier is specified.

Further options can be viewed using the help option (`--help` or `-h`) or in the official documentation (http://mng.bz/095J). If you execute `dotnet publish` from within the folder containing the project file, the published output will be generated at \bin\Debug\net6.0\publish in `debug` mode as a framework-dependent deployment targeting the runtime specified in the project file. `Debug` mode is not optimal for deployment, so at the very least, you should specify the configuration as `Release` when using the `dotnet publish` command, using the following option:

```
dotnet publish -c Release
```

Publishing to a local folder is the only option provided by the CLI commands. Most often, you will then use FTP or a similar tool to transfer the published output to the hosting location. Visual Studio, on the other hand, enables publishing to other targets as well as a local folder, which we will look at next.