```
        "Password": "testpassword"    ❸
      }
    }
  }
}
```

❶ Creates a configuration section at Kestrel:Certificates:Default

❷ The relative or absolute path to the certificate

❸ The password for opening the certificate

The preceding example is the simplest way to replace the HTTPS certificate, as it doesn't require changing any of Kestrel's defaults. You can use a similar approach to load the HTTPS certificate from the OS certificate store (Windows or macOS), as shown in the "Replace the default certificate from configuration" documentation mentioned previously (http://mng.bz/wvv2).

WARNING Listing 28.1 hardcoded the certificate filename and password for demonstration, but you should never do this in production. Either load these from a configuration store like user-secrets, as you saw in chapter 10, or load the certificate from the local store. Never put production passwords in your appsettings.json files.

All the default ASP.NET Core templates configure your application to serve both HTTP and HTTPS traffic, and with the configuration you've seen so far, you can ensure that your application can handle both HTTP and HTTPS in development and in production.

However, whether you use HTTP or HTTPS may depend on the URL users click when they first browse to your app. For example, imagine you have an app that listens using the default ASP.NET Core URLs: http://localhost:5000 for HTTP traffic and https://localhost:5001 for HTTPS traffic. The HTTPS endpoint is available, but if a user doesn't know that and uses the HTTP URL (the default option in browsers), their traffic is unencrypted. Seeing as