`Host.CreateDefaultBuilder()` helper method you learned about in chapter 30 to create an `IHostBuilder`.

NOTE .NET 8 will change the worker service template to use a new type, `HostApplicationBuilder`, which is analogous to `WebApplicationBuilder`. `HostApplicationBuilder` brings the familiar script-like setup experience of minimal hosting to worker services, instead of using the callback-based approach of `IHostBuilder`.

You configure your DI services in Program.cs using the `ConfigureServices()` method on `IHostBuilder`, as shown in listing 34.7. This method takes a lambda method, which takes two arguments:

- A `HostBuilderContext` object. This context object exposes the `IConfiguration` for your app as the property `Configuration`, and the `IHostEnvironment` as the property `HostingEnvironment`.
- An `ISeviceCollection` object. You add your services to this collection in the same way you add them to `WebApplicationBuilder.Services` in typical ASP.NET Core apps.

The following listing shows how to configure EF Core, the exchange rates typed client from chapter 33, and the background service that saves exchange rates to the database, as you saw in section 34.1.2. It uses C#'s top-level statements, so no `static void Main` entry point is shown.