- The `LinkGenerator` can be used to generate URLs from minimal API endpoints. Provide the name of the endpoint to link to and any required route values to generate an appropriate URL.
- You can use the `RedirectToRoute` method to generate URLs while also generating a redirect response. This approach is useful when you don't need to reference the URL in code.
- By default, URLs are generated using the same casing as the route template and any supplied route parameters. Instead, you can force lowercase URLs, lowercase query strings, and trailing slashes by customizing `RouteOptions`, calling `builder.Services.Configure<RouteOptions>()`.
- You can change the settings for a single URL generation by passing a `LinkOptions` object to the `LinkGenerator` methods. These methods can be useful when you need to differ from the defaults for a single endpoint, such as when you're trying to match an existing legacy route.