- `IOptions<T>`—The instance is created once, when first needed. It always contains the configuration from when the object instance was first created.
- `IOptionsSnapshot<T>`—A new instance is created, when needed, if the underlying configuration has changed since the last instance was created.

WARNING `IOptionsSnapshot<T>` is registered as a scoped service, so you can't inject it into singleton services; if you do, you'll have a captive dependency, as discussed in chapter 9. If you need a singleton version of `IOptionsSnapshot<T>`, you can use a similar interface, `IOptionsMonitor<T>`. See this blog post for details: http://mng.bz/9Da7.

`IOptionsSnaphot<T>` is set up for your options classes automatically at the same time as `IOptions<T>`, so you can use it in your services in exactly the same way. The following listing shows how you could update your display-settings API so that you always get the latest configuration values in your strongly typed `AppDisplaySettings` options class.

Listing 10.9 Injecting reloadable options using `IOptionsSnapshot<T>`

```
app.MapGet("/display-settings",
    (IOptionsSnapshot<AppDisplaySettings> options) =>    ❶
{
    AppDisplaySettings settings = options.Value;         ❷

    return new
    {
        title = settings.Title,                          ❸
        showCopyright = settings.ShowCopyright,          ❸
    };
});
```

❶ IOptionsSnapshot<T> updates automatically if the underlying configuration values change.

❷ The Value property exposes the POCO settings object, the same as for IOptions<T>.

❸ The settings match the configuration values at that point in time instead of at first run.