When you install Docker on a Linux operating system, you get the full Docker Engine on your Linux host. However, if you install either *Docker Desktop for Mac* or *Docker Desktop for Windows*, only the Docker client is installed on your macOS/Windows host. Under the hood, a lightweight virtual machine is configured with Linux, and the Docker server component is installed on that machine. As a user, you will get almost the same experience as on a Linux machine; you will hardly notice any difference. But in reality, whenever you use the Docker CLI to perform operations, you are actually interacting with a Docker server on a different machine (the virtual machine running Linux).

You can verify this yourself by starting Docker and running the `docker version` command. You'll notice that the Docker client is running on a `darwin/amd64` architecture (on macOS) or on `windows/amd64` (on Windows), while the Docker server is running on `linux/amd64`.

```
$ docker version
Client:
 Cloud integration: v1.0.24
 Version:           20.10.14
 API version:       1.41
 Go version:        go1.16.15
 Git commit:        a224086
 Built:             Thu Mar 24 01:49:20 2022
 OS/Arch:           darwin/amd64
 Context:           default
 Experimental:      true

Server:
 Engine:
  Version:          20.10.14
  API version:      1.41 (minimum version 1.12)
  Go version:       go1.16.15
  Git commit:       87a90dc
  Built:            Thu Mar 24 01:45:44 2022
  OS/Arch:          linux/amd64
  Experimental:     false
```

Docker provides support for architectures other than AMD64. For example, if you use a MacBook with Apple Silicon (ARM-based chips), you'll find your Docker client running on a `darwin/arm64` architecture and the Docker server on `linux/arm64`.

2.3.2 Running a Spring application as a container