There are a few ways to access properties from a Java class, as shown in figure 4.3. The most generic approach is based on the `Environment` interface, which you can autowire wherever you need access to an application property. For example, you can use it to access the value for the `server.port` property as follows:

```
@Autowired
private Environment environment;

public String getServerPort() {
  return environment.getProperty("server.port");
}
```




Figure 4.3 You can access Spring properties in different ways.

Properties can also be injected without explicitly invoking the `Environment` object. Just like you use the `@Autowired` annotation