change the context, you can run `kubectl config use-context <context-name>`. A list of all the contexts available can be retrieved from `kubectl config get-contexts`.

Open a Terminal window, go to your Polar Deployment project (polar-deployment), and navigate to the kubernetes/platform/production/argocd folder. You should have copied that folder over to your repository when you set up the production cluster. If that's not the case, please do so now from the source code repository accompanying this book (Chapter15/15-end/polar-deployment/platform/production/argocd).

Then run the following script to install Argo CD into the production cluster. Feel free to open the file and look at the instructions before running it:

```
$ ./deploy.sh
```

TIP You might need to make the script executable first, with the command `chmod +x deploy.sh`.

The deployment of Argo CD consists of several components, including a convenient web interface where you can visualize and control all the deployments controlled by Argo CD. For now, we'll use the CLI. During the installation, Argo CD will have autogenerated a password for the admin account (the username is `admin`). Run the following command to fetch the password value (it will take a few seconds before the value is available):

```
$ kubectl -n argocd get secret argocd-initial-admin-secret \
    -o jsonpath="{.data.password}" | base64 -d; echo
```

Next, let's identify the external IP address assigned to Argo CD server:

```
$ kubectl -n argocd get service argocd-server

NAME            TYPE           CLUSTER-IP     EXTERNAL-IP
argocd-server   LoadBalancer   10.245.16.74   <external-ip>
```