anymore, run `minikube tunnel --profile knative` before calling the application:

```
$ http http://quote-function.default.127.0.0.1.sslip.io
```

Knative provides an abstraction on top of Kubernetes. However, it still runs Deployments, ReplicaSets, Pods, Services, and Ingresses under the hood. This means you can use all the techniques you learned in the previous chapters. For example, you can configure Quote Function through ConfigMaps and Secrets:

```
$ kubectl get pod

NAME                                                  READY   STATUS
pod/quote-function-00001-deployment-c6978b588-llf9w   2/2     Running
```

If you wait for 30 seconds and then check for the running Pods in your local Kubernetes cluster, you'll see there are none, because Knative scaled the application to zero due to inactivity:

```
$ kubectl get pod
No resources found in default namespace.
```

Now try sending a new request to the application on `http http://quote-function.default.127.0.0.1.sslip.io`. Knative will immediately spin up a new Pod for Quote Function to answer the request:

```
$ kubectl get pod

NAME                                              READY   STATUS
quote-function-00001-deployment-c6978b588-f49x8   2/2     Running
```