


Figure 4.7 Example OpenTelemetry pipeline for traces and metrics

configuration for connecting to the OpenTelemetry collector via the `OTEL_EXPORTER_OTLP_ENDPOINT` environment variable.

Listing 4.5 Docker Compose configuration snippet for `ho11y`

```
ho11y:
    image: public.ecr.aws/mhausenblas/ho11y:stable
    ports:
    - "8765:8765"
    environment:
    - "OTEL_EXPORTER_OTLP_ENDPOINT=otel-collector:4317"
    - "OTEL_RESOURCE_ATTRIB=ho11y"
    - "HO11Y_INJECT_FAILURE=enabled"
    depends_on:
    - otel-collector
```

The port for the HTTP API

Configures the downstream OpenTelemetry collector (for OTLP over gRPC)

Listing 4.6 shows the OpenTelemetry collector using a custom configuration (`otel-collector-config.yaml`) we discuss a little later. We expose all these ports there to make them accessible from outside of Docker— that is, you can troubleshoot from the host machine more easily with this setup.

Listing 4.6 Docker Compose configuration snippet for the OpenTelemetry collector

```
otel-collector:
    image: otel/opentelemetry-collector-contrib:0.55.0
    command: ["--config=/conf/otel-collector-config.yaml"]
    volumes:
    - ./otel-config.yaml:/conf/otel-collector-config.yaml
    ports:
    - "4317:4317"
    - "8888:8888"
```

The collector config to use

The config file (mounted into the container from the host file system)

4317 is the OTLP receiver port.

8888 is the port the collector uses for metrics self-telemetry.