


Figure 7.16 Making a request to the sample server

7.5.2 Sending requests to the local server

In addition to sending cross-origin requests, test-cors.org can send requests to its own local server. This local server can be configured using the parameters in the response panel, which control how the server responds to CORS requests.

Let's configure the local server to respond to the same `GET` request configured in the previous section. Choose the Local tab in the response panel. This shows the options that can be configured in the local server. If you click Send Request, you'll see that the error event handler will fire. This code throws an error because you haven't configured the local server to support cookies and custom headers.

Each box under the Local tab corresponds to a particular CORS header. You can add support for cookies and custom headers by first clicking the Allow Credentials