A couple of attributes may need your attention. The `name` is the instance's name, which defaults to your computer's name. You can change by tweaking the configuration (as shown later).

The second property of importance is `cluster_name`, indicating the name of the cluster this node has joined. Again, Elasticsearch provides defaults, so the current cluster's name is `elasticsearch`, set by default.

A.1.3 Starting up on macOS

Download the macOS binary (tar.gz) and uncompress it to your preferred location, say /Users/<*username*>/DEV/platform. Open a terminal, and navigate to the bin directory in your installation folder:

```
$>cd ~/DEV/platform/elasticsearch/bin
```

Execute the `elasticsearch` run script:

```
$>./elasticsearch
```

This brings up the Elasticsearch server in a single-node cluster. The output to the console with the message "Server Started" indicates that the server was started successfully. Navigate to http://localhost:9200 on your favorite browser once the server is up and running. You should see the response shown in figure A.2.

```
mkonda@mkmac bin % curl http://localhost:9200
{
  "name" : "mkmac.local",
  "cluster_name" : "elasticsearch",
  "cluster_uuid" : "0a_3154xTjW9m-NELJE4fA",
  "version" : {
    "number" : "7.11.2",
    "build_flavor" : "default",
    "build_type" : "tar",
    "build_hash" : "3e5a16cfec50876d20ea77b075070932c6464c7d",
    "build_date" : "2021-03-06T05:54:38.141101Z",
    "build_snapshot" : false,
    "lucene_version" : "8.7.0",
    "minimum_wire_compatibility_version" : "6.8.0",
    "minimum_index_compatibility_version" : "6.0.0-beta1"
  },
  "tagline" : "You Know, for Search"
}
```

Figure A.2 Server response using cURL on macOS

Accessing the server using cURL

In addition to accessing Elasticsearch's URL via browser, you can use cURL (command-line URL invocation utility) to interact with the server. Unix users love using cURL for hitting HTTP URLs. It's a very popular and useful command-line utility to talk to servers over HTTP. Most Unix-based systems have the utility installed by default