Table 4-8. *ini config directives*

ini directive	Purpose
error_reporting	Sets the reporting error level (typically using E_* constants)
display_errors	Enable/disable the sending of errors as program output
log_errors	Enable/disable error logging
error_log	File path of the error logging file, or syslog
html_errors	Wrap error messages in HTML tags for viewing in a browser

The full documentation for error-related configuration can be found at https://www.php.net/manual/en/errorfunc.configuration.php

Error Handling

If necessary, you can add to, or override, the default error handling behavior for a certain set of error levels. This can be useful for injecting your own logic into error-handling events. The built-in function set_error_handler() accepts a callable (e.g., an anonymous function, a string matching a declared function name, etc.), and an error level expression that matches the error levels you wish your callable to be invoked for. You cannot define a handler for E_ERROR (fatal) or any of the startup or compile-time error levels such as E_PARSE, E_COMPILE_ERROR, etc. If the handler callable returns false, then the default handler will be invoked immediately afterwards (return true to end error handling once yours is done).

```
// error_handler.php
error_reporting(E_ALL);
set_error_handler(function ($errno, $errstr, $file, $line) {
    switch ($errno) {
        case E_WARNING:
            print "WARNING!!! {$errstr}" . PHP_EOL;
            break;
        case E_USER_NOTICE:
            print "Just a notice... {$errstr}" . PHP_EOL;
            break;
    }
```