```
<?
  $Link = msql_connect("msql.clearink.com");

  if(msql_drop_db("store", $Link))
  {
    print("Database deleted!");
  }
  else
  {
    print("Database not deleted: ");

   print(msql_error());
  }

 msql_close($Link);
?>
```

string msql_error()

Use msql_error to retrieve the last error message returned by an mSQL function.

array msql_fetch_array(integer result, integer type)

The msql_fetch_array function returns an array of the data for the current row. The result argument is as returned by msql_query. By default, result columns are returned in two elements each: one referenced by number and one referenced by field name. The optional type argument controls which elements are created. MSQL_NUM signals that only numbered elements be created. MSQL_ASSOC signals that only named elements be created. If you want both, you can explicitly request it with MSQL_BOTH.

Compare this function to msql_fetch_row and msql_fetch_object.

```
<?
  $Link = msql_connect("msql.clearink.com");
  msql_select_db("store", $Link);

  $Query = "SELECT * FROM customer";
  $Result = msql_query($Query, $Link);

  //fetch each row
  while($Row = msql_fetch_array($Result, MSQL_ASSOC))
  {
    print($Row["FirstName"] . "<BR>\n");
  }

  msql_close($Link);
?>
```

object msql_fetch_field(integer result, integer field)

The msql_fetch_field function returns an object with properties that describe the specified field. The field argument may be left out, and the next unfetched field will be returned. The properties of the object are listed in Table 6.