string ociresult(integer statement, value column)

Use ociresult to get the value of a column on the current row. The column may be identified by number or name. Columns are numbered starting with 1. Results are returned as strings, except in the case of LOBs, ROWIDs, and FILEs.

boolean ocirollback(integer connection)

Use ocirollback to issue a rollback operation on the given connection. By default, calls to ociexecute are committed automatically, so be sure to override this functionality if you wish to use ocirollback.

integer ocirowcount(integer statement)

The ocirowcount function returns the number of rows affected by an update, insert, or delete.

string ociserverversion(integer connection)

Use ociserverversion to get a string describing the version of the server for a connection.

integer ocisetprefetch(integer statement, integer size)

The ociprefetch function sets the size of a buffer that Oracle uses to prefetch results into. The size argument will be multiplied by 1024 to set the actual number of bytes.

string ocistatementtype(integer statement)

Use ocistatementtype to get a string that describes the type of the statement. The types you can expect are ALTER, BEGIN, CREATE, DECLARE, DELETE, DROP, INSERT, SELECT, UNKNOWN, and UPDATE.

boolean ora_bind(integer cursor, string variable, string parameter, integer length, integer type)

The ora_bind function binds a PHP variable to a parameter in an Oracle query. This causes data to flow between the two entities. You must call ora_parse before binding any variables. The type parameter is optional. It specifies whether data may go only into or out of the Oracle parameter. By default, data may go both ways. The type may be defined using the following constants: ORA_BIND_IN, ORA_BIND_INOUT, ORA_BIND_OUT.