integer dbase_numfields(integer database)

The dbase_numfields function returns the number of fields for the given database.

integer dbase_numrecords(integer database)

The dbase_numrecords function returns the number of records in the database.

integer dbase_open(string filename, integer mode)

Use dbase_open to get a dbase identifier. This integer is needed for identifying which database to operate on. The mode may be 0 for read-only, 1 for write-only, or 2 for allowing both reading and writing. FALSE is returned if the database cannot be opened.

boolean dbase_pack(integer database)

When rows are deleted in a dbase database, they are simply marked for deletion. Use the dbase_pack function to permanently remove these rows, thus packing the database.

```
<?
  //connect to database
  $db = dbase_open("customer.dbf", 2);

  //removed rows marked for deletion
  dbase_pack($db);

  //close connection
  dbase_close($db);
?>
```

boolean dbase_replace_record(integer database, array record, integer record_number)

Use dbase_replace_record to change the contents of a record. The record argument must have one element for each field defined in the database. Record numbers start counting at one.

```
<?
  $db = dbase_open("customer.dbf", 2);

  $Record = array("John Smith", 200.00, "19990901","Y");
  dbase_replace_record($db, $Record, 1);

  dbase_close($db);
?>
```