... and these for startup or compile-time:

Table 4-7. *Startup/compile time error constants*

Constant	Definition
E_CORE_ERROR	Unrecoverable, startup error
E_CORE_WARNING	Recoverable, startup error
E_COMPILE_ERROR	Unrecoverable, compile-time, script parsed as legal syntax
E_COMPILE_WARNING	Recoverable, compile-time, script parsed as legal syntax
E_PARSE	Unrecoverable, compile-time, syntax error in code

Each of these constants is an integer value, and these can be combined with bitwise operators to form logical expressions from multiple constants. For example, `E_WARNING | E_NOTICE & ~E_DEPRECATED` means "error level of warning or notice and not deprecated." These expressions are used either in configuration (as ini directives) or as arguments to runtime function calls.

Error Control

You can tell PHP which errors you want to see (or ignore) by setting the reporting level with either the `error_reporting` ini directive...

```
// php.ini
; use bitwise operators AND & and NOT ~ to enable all except E_DEPRECATED
error_reporting = E_ALL & ~E_DEPRECATED
```

... or at runtime with the `error_reporting()` function:

```
// deliberate Warning error
print $undefVar;

// report fatal Error runtime errors only
error_reporting(E_ERROR);
print $anotherUndefVar;

Output:
PHP Warning:  Undefined variable $undefVar...
```