```
    server_name yourdomain.com;  # Replace with your domain or IP
    root /var/www/laravel12/public;

    index index.php index.html;

    location / {
        try_files $uri $uri/ /index.php?$query_string;
    }

    location ~ \.php$ {
        include snippets/fastcgi-php.conf;
        fastcgi_pass unix:/run/php/php8.4-fpm.sock;
        fastcgi_param SCRIPT_FILENAME $document_root$fastcgi_script_name;
        include fastcgi_params;
    }

    location ~ /\.ht {
        deny all;
    }
}
```

Enable and reload:

```
sudo ln -s /etc/nginx/sites-available/laravel12 /etc/nginx/sites-enabled/
sudo nginx -t
sudo systemctl reload nginx
```

17.7.4.7 Step 7: Set Permissions

After we copied the files, we need to set the correct permissions for the storage and bootstrap/cache directories:

```
sudo chown -R www-data:www-data /var/www/laravel12
sudo chmod -R 755 /var/www/laravel12/storage /var/www/laravel12/bootstrap/cache
```

Change `laravel12` to your actual project directory. The `www-data` user is the default user for Nginx and PHP-FPM on Ubuntu.

This ensures that the web server can write to these directories.

17.7.4.8 Step 8: Configure Firewall (Optional)

To allow HTTP and HTTPS traffic, you can use UFW (Uncomplicated Firewall):

```
sudo ufw allow OpenSSH
sudo ufw allow 'Nginx Full'
sudo ufw enable
```

If you are using a cloud provider, make sure to allow HTTP and HTTPS traffic in the security group settings.