You may define a plain-text view for the mail message by supplying the view name to the **view** method as the second member of an array:

```
public function toMail(object $notifiable): MailMessage
{
 return (new MailMessage)->view(
  [‘emails.name.html’, ‘emails.name.plain’],
  [‘order’ => $this->order]
 );
}
```

Customizing Email Components

The sender / from address of emails is set by default in the **config/mail.php** configuration file. However, you may use the **from** method to provide the from address for a single notification:

```
public function toMail(object $notifiable): MailMessage
{
 return (new MailMessage)
     ->from(‘abc@example.com’, ‘Sample Name’)
     ->line(‘…’);
}
```

The notification system will automatically check for an **email** attribute on your notifiable object when sending alerts over the **mail** channel. By establishing a **routeNotificationForMail** method on the notifiable entity, you may specify which email address is used to deliver the notification:

```
<?php
namespace App\Models;
use Illuminate\Foundation\Auth\User as Authenticatable;
use Illuminate\Notifications\Notifiable;
use Illuminate\Notifications\Notification;
class User extends Authenticatable
{
 use Notifiable;
 public function routeNotificationForMail(Notification
 $notification): array|string
 {
```