(access point) changes. It's fired when a new connection is established or an existing connection is lost, using the EXTRA_NEW_STATE Boolean extra, which returns true in the former case.

- **NETWORK_STATE_CHANGED_ACTION:** Fired whenever the Wi-Fi connectivity state changes. This Intent includes two extras: the first EXTRA_NETWORK_INFO includes a NetworkInfo object that details the current network state, while the second EXTRA_BSSID includes the BSSID (Basic Service Set IDentifier) of the access point you're connected to.
- **RSSI_CHANGED_ACTION:** You can monitor the current signal strength of the connected Wi-Fi network by listening for the RSSI_CHANGED_ACTION Intent. This Broadcast Intent includes an integer extra, EXTRA_NEW_RSSI, that holds the current signal strength. To use this signal strength, use the calculateSignalLevel static method on the Wi-Fi Manager to convert it to an integer value on a scale you specify..

8.2 Monitoring Active Connection Details

Once an active network connection has been established, use the getconnectionInfo method on the Wi-Fi Manager to find information on the active connection's status. The returned wifiInfo object includes the SSID (Service Set Identifier), BSSID, Mac address and IP address of the current access point, as well as the current link speed and signal strength.

```
WifiInfo info = wifi.getconnectionInfo();
      if (info.getBSSID()!= null) {
           int strength = WifiManager.calculateSignalLevel(info.
getRssi(), 5);
        int speed = info.getLinkSpeed();
        String units = WifiInfo.LINK_SPEED_UNITS;
        String ssid = info.getSSID();

      String cSummary = String.format("Connected to %s at %s%s.
Strength %s/5",
                                               ssid, speed, units,
strength);
      }
```

8.3 Scanning for Hotspots

You can also use the Wi-Fi Manager to conduct access point scans using the startScan method. An Intent with the SCAN_RESULTS_AVAILABLE_