Remember, when we just add the JList reference to the Container, we do not automatically get scrolling. For that, you need to add the JList to a JScrollPane. Notice, although we specified a visible limit of 7 rows—we're seeing 10. What gives? The setVisibleRowCount() method only takes effect when the list is in a scroll pane.

You recall, the JList delegates its labor to other classes that actually do the work. For example, the JList does not manage the data handling—the references—to the objects it displays. Instead, all instances of JList delegate the management of the data to an object that implements the ListModel interface. To facilitate this model, you can construct instances of a JList using the following Constructors:

- public JList(ListModel)
- public JList(Object[])
- public JList(Vector)

After you have constructed an instance of the class JList, you can change what is displayed with the following:

- public void setModel(ListModel)
- public void setListData(Object[])
- public void setListData(Vector)

These methods allow you to change the entire contents of the list in one motion. Changing individual elements is not so easy. Since the JList does not maintain its own data, it cannot help you change individual elements in the list. To accomplish that, you have to go to where that data is stored.

- You have to directly manipulate the list's model.
- All of these "models" must implement the ListModel interface.

"This interface defines the methods that components like JList use to get the value of each cell in a list and the length of the list." Logically the model is a vector. Its indexes vary from 0 to ListDataModel.getSize() - 1. Any change to the contents or length of the data model must be reported to all of the

10.12.1 ListDataListeners—the controllers

Adding or Removing An Item from the JList

Whenever you add or remove an item from your list, that is another type of event. To track that event, you use the object

ListDataListener

- If you want to change an item in a JList, you have to get its model, and go through the interface

ListDataListener