



Troubleshooting

Problems with installing Windows Me, printer not being detected, converting PDF files to word, configuring a modem in Linux...solutions to these and other problems

Applications

+ Voice error

Whenever I open IBM ViaVoice 98, it gives me the following error, 'VOICEPAD caused an invalid page fault in module MFC42.DLL'. How do I get rid of this message?

Kovid,
via e-mail

R This error could occur because the mfc42.dll file is missing, corrupted or it's the wrong version. This file is required by many applications and usually most applications come along with their own copy of the file, which is placed in the Windows\System folder, thus causing problems for other applications.

To fix this problem, the file required by Voice Pad should be placed in the ViaVoice directory. You should follow these steps: Make sure that you can see all the files (hidden as well as system) in your system. Then rename mfc42.dll in C:\Windows\System to mfc42.dll.old. Reboot the system before this step to ensure that no program is using this file. Next, reinstall ViaVoice. Now you will find a new copy of mfc42.dll file in C:\Windows\System. Copy this file to the viavoice\bin directory. Finally, rename the mfc42.dll.old file back to mfc42.dll in C:\Windows\System. This should get rid of the error.

Linux


+ Modem in Linux

How do I go about configuring a modem in Linux Red Hat 7.0?


Aji,
via e-mail

R Configuring a modem under Linux is pretty much the same as it is in Windows. All you need to know is which port it is installed on.

A point to note is that COM1 in Windows is ttyS0 in Linux, COM2 is ttyS1, and so on. Once you figure this out, you should symlink this device to /dev/modem, so as



Disabling existing DNS servers in Kppp



Configuring wvdial

to avoid confusion later on. Use the command `ln -s /dev/ttyS0 /dev/modem`.

Now you could use any one of the diallers that are available in Linux. One of the best utilities is Kppp, which is very easy to configure. Those who like command line utilities could use wvdial. To configure wvdial, you need to use the command `wvdialconf /etc/wvdial.conf`. You have a host of configuration options for wvdial. You should see the man pages for wvdial for more information. Also note that if you are using utilities like wvdial you will have to set the DNS server to that of your ISP. This can be done using netconf. This can be avoided if you are using Kppp, as it has the option of accepting your ISP's DNS server in its configuration, with your current DNS server being disabled.

Windows

+ Me doesn't install

Whenever I try to install Windows Me on my Windows 98SE, setup runs well till ten per cent of it is complete but then it shows the following message, 'Setup cannot copy the files to your system. error-Suo325.'

Ibadat,
via e-mail

R This problem arises when a corrupted .cab file has been copied to the hard disk. This corruption can be caused either by a virus or by failing hardware, but the most likely reason is a scratched, dirty or damaged CD-ROM. Try cleaning the CD-ROM or replace it. Also make sure that your PC is not infected by a virus. If this does not help, you need to check the possibility of failing hardware.

Linux

+ Of native and swap partitions

I recently upgraded my system to a 20 GB HDD. I have five disk partitions that contain 3.99, 3.65, 3.65, 3.65 and 3.64 GB, respectively. I would like to install Red Hat Linux 6.2 in the last partition of 3.64 GB. But when I run the Linux setup and allocate swap and native partitions, it says, 'Boot Partition too big' and does not allocate the native partition, although it does allocate the swap partition. What should I do?

Hariharan,
via e-mail

R This is a common problem when the hard disk size is too big. The error occurs when the boot partition falls outside the 1024 cylinder area of the hard disk. You should try the following. Delete all the partitions that you have made for Linux, that is, swap partitions. Then make a /boot partition of around 10-16 MB of Ext2 type. Now go ahead with making all the other partitions, namely, the /Linux Ext2 type and the swap partitions. This should solve the problem. →