



Just select Microsoft Office 2000 and click on the 'Add' button to install it

acceptance to typical installation, etc. Now, you just need to restart the CrossOver emulator. Once the installation is completed, you can work with your most desired Microsoft Office applications, such as Word and Excel. These can be accessed by going to **Main menu > Windows Application Menu**.

To remove an application, go to **Main menu > CrossOver Office > CrossOver Office Setup**. Select the installed software, and click on the Remove button to start the application's un-installation program.

## 2 Access Windows Files automatically


Most users start with a dual boot system when they install Linux. Hence, transferring or accessing files created while working in Windows is the first problem faced. For example, you wish to open a Microsoft Word file from your Windows partition. Solve this by loading the Windows partition, using the mount command. To use the mount command, there are two essential requirements: First, you should have a local folder where you can map the Windows partition. And second, the physical address of the Windows partition. As far as local folder is concerned, you can create a new folder, called 'win-

dows', within the /mnt folder, using **mkdir /mnt/windows**.

But, to find the physical address of your Windows partition, you will have to use a utility such as Hardware Browser.

Now, you have a local folder /mnt/windows, as well as a physical address of your windows partition /dev/hdb1. Now, at the command prompt, type **mount -t vfat /dev/hdb1 /mnt/windows**.

You need root permission to issue the command. So, log in as root, or change to root, using the **su** command. The mount command will load the Windows partition once. Hence, you will have to execute the mount command again, whenever you restart your PC. To avoid this, change



The fstab file lists all the available partitions and their mount points

the File System Table i.e. /etc/fstab. Open this file with any text editor such as vi, gedit, etc. This file is formatted in 6 columns separated by spaces. You need to append the following line

```
/dev/hdb1 /mnt/windows vfat
auto,umask=0 0 0
```

From now on, whenever you want to access the files of your Windows folder, go to /mnt/windows.

## 3 Share files and printers using Samba

With Microsoft's SMB (Server Message Block), it became easy to access Windows shares on a Linux PC, but the configuration was a headache. Now, SWAT (Samba Web Administration Tool) reduces this headache, by providing a Web-based utility, to manage the Samba server.

### Start the service

First of all, you need to start the SWAT service. To do so, first modify the line 'disable = yes' to 'disable = no' within the file **/etc/xinet.d/swat**, then restart the xinetd

**Bonus TIP 1**

## Configure services

ntsysv is a simple graphical utility to activate and deactivate services. It gives you complete control as to which services should, or should not be running. First, type **ntsysv** at the terminal window, and press **[Enter]**.

You will see a list of services available that you can either enable, or disable. The services that are already enabled are the ones, which start when your



ntsysv lists all the services available on your Linux PC

PC boots up. Select, or unselect all the services needed, and press OK. Restart the PC for the changes to come into effect.

By default, the configuration is affected only to the current runlevel. If you wish to make similar changes to more than one runlevel, use the command: **ntsysv --level 35**.


The configuration will affect all the runlevel number(s) specified after the --level option. In the example shown, the runlevel 3 and 5 will be affected.

service by executing the following command at the prompt: **/etc/rc.d/inet.d/xinetd restart**.

Configure the SWAT service to run automatically every time the PC starts, by



You can adjust the Global settings in SWAT



Partitions are listed as /dev/hdx