




If you are using Red Hat Linux 9, then you can easily add the components using the Package Management tool

ry for the Apache server. Verify this information in the `/etc/httpd/conf/httpd.conf` file that specifies this path as DocumentRoot `"/var/www/html"`. To uncompress Nola, go to **K menu > System Tools > Terminal** and type `'tar zxvf nola-1.1.2.tar.gz/var/ www/html/'`.

Next, change the ownership of this folder so that Apache can access this directory. When installed, Apache creates a user, called apache, who is a member of the group apache. Enter the `'hown -R apache:apache /var/www/html/nola/'` command to change the ownership to the user apache.

After this, enter `'service mysqld start'` and `'service httpd start'` to start the Apache and MySQL services. It's now time to configure MySQL by creating a database that can be used by Nola. For this, Nola has SQL scripts that you just need to execute. At the terminal, type `'mysql -p < /var/www/html/nola/documentation/scripts/MySQL/database.sql'` to create a database named Noguska. Now, you need to fill up this database with basic data such as default user, etc, so that Nola runs properly. Type `'mysql -p noguska </var/www/html/nola/documentation/scripts/MySQL/filldata.sql'` to do so.

Now, update the MySQL login information in the `/var/www/html/nola/includes/define.php` file. Change the default values of username and password to those specified for MySQL. If you have not changed the default values while installing MySQL, you don't need to change anything in the defines.php file.

Add the following lines in the

`/var/rc.local` file to ensure that the mysqld and httpd services start every time you boot up your Linux system:

```
service mysqld start
service httpd start
sleep 8
clear
```

The last two lines guarantee that the services start in the background without distracting you.

That's it! Now, type `'http:// localhost/nola'` in the address bar of the Web browser, and the login prompt greets you. Log in using the default admin account with 'password' as its password. You will see the navigation bar on the left, and the main pages in the middle. At times, images

just don't appear, leaving you with nothing to do. In this case, you may disable them and switch to text mode. To do so, open the file `/var/www/html/nola/includes/defines.php` and look for the section named `'* Menu section'`. It should have these lines:

```
//show menu items as images
define('MENU_SHOW_AS_IMAGE', '1');
//show explain items
define('EXPLAIN_SHOW_AS_IMAGE', '1');
//show icons on explain* sub-
menus
define('EXPLAIN_SHOW_PIC-
TURES', '1');
```

Change all the '1's in the above entries to '0's.

Now, when you refresh the Nola start page in the browser, it displays only text for navigation. Thus, the page takes lesser time to load, and the interface is simpler than before.

Setting up Nola

Before using Nola for your business operations, you need to set up certain things. First, go to the Admin section and edit the company name (by default, it is 'My Company - Edit Me') by clicking on Client Companies. Click the 'Edit Selected Company' button to enter your company's

information. If you create multiple companies, these are listed at the top of the navigation bar as a drop-down list.

Next, change the default admin password by clicking Users and Rights. Create a new user by clicking on 'Add new user'. If you enable the Supervisor checkbox, the user gets administrative rights. Check the other checkboxes to assign users the rights to view, write and set up Nola modules such as Accounts Payable, Accounts Receivable, General Ledger, Payroll and Inventory.

The Admin section also has options to create document categories. Here, you can specify the categories that users can upload. This is helpful when a user wants to upload a document such as a product's image that pertains to a particular transaction. Finally, this section also lets you import a customer list from a Comma Separated Values (CSV) file. The file structure should be as specified in the Help section of this page.

General ledger

Create financial accounts once you are through with the Admin section. By default, the basic account types such as Capital, Expenses, Sales, etc, are inbuilt. To create accounts of a different kind, go to **General Ledger > Setup Function for General Ledger**. However, Nola cautions you that "this should only be done under the

Module Access			
Module	Read	Write	Setup
Accounts Payable:	☒	☒	☒
Accounts Receivable:	☒	☒	☒
General Ledger:	☒	☒	☒
Payroll:	☒	☒	☒
Inventory:	☒	☒	☒

Create uses with specific rights, under the Admin section of Nola