

Windows XP

Hide Users On The Welcome Screen

When you add an account for certain users in Windows XP, their user names appear on the Welcome Screen. Sometimes a user needs to be added to a computer because they need access via a network to resources on the machine, but he or she will not be physically logging in to the computer.


In such cases, you can remove his or her name from the Welcome Screen, while keeping the user account.

To do this, open the Registry Editor, go to HKEY_LOCAL_MACHINE\SOFTWARE\Microsoft\Windows NT\CurrentVersion\Winlogon\SpecialAccounts\UserList\ Right-click in the empty space in the right pane and create a new DWORD Value. Name this new value 'Username' and enter '0' as the data value.

If you want to enable this user again on the Welcome Screen, either double-click the 'Username' value and change the Value Data to '1', or delete the value.

Remove 'Logoff' From The Start Menu

You might want to remove the 'Logoff' button from the Start Menu if you never use it. This involves a registry tweak. Go to the Start Menu, click 'Run', and type in "regedit". This will take you to the Registry Editor. (In all the tips that follow, we won't again mention how to start the Registry Editor.)



Remove 'Logoff' from the Start Menu

Tips & Tricks

SECRETS THAT KEEP YOU AHEAD IN THE RACE

GENERAL TIPS

Windows XP

83

30 MINUTES EXPERT

Create Your Own 'Best Of'

Playing Moments

85

DVD Movies On Your Pocket PC

88

Go to HKEY_CURRENT_USER\SOFTWARE\Microsoft\Windows\CurrentVersion\Policies\Explorer. Right-click in the right pane and create a new DWORD value. Name this value 'StartMenuLogoff'. Give it a value of '1' and restart your computer. 'Logoff' will no longer be visible in the Start Menu.

Bypass The Recycle Bin When Deleting Files

Right-click on the Recycle Bin and choose 'Properties'. In the 'Global' tab, check the box that says "Do not move files to the Recycle Bin...." That's it. No more taking out the garbage!

Get Rid Of The Recycle Bin

XP offers you a very clean desktop. Clearing it up is fairly simple; however, there's one item that sticks out like a sore thumb on your otherwise clean desktop—the Recycle Bin. You cannot get rid of it by just deleting it or through any menu options. Deleting it from your desktop needs a Registry tweak.

In the Registry Editor, delete the following key: HKEY_LOCAL_MACHINE\SOFTWARE\Microsoft\Windows\CurrentVersion\Explorer\Desktop\NameSpace\{645FF040-5081-101B-9F08-00AA002F954E}

Restart your computer. The Recycle Bin will no longer be on your desktop.

Alternatively, instead of deleting the aforementioned key, you can change the value for {645FF040-5081-101B-9F08-00AA002F954E} to '1' at HKEY_CURRENT_USER\Software\Microsoft\Windows\CurrentVersion\Explorer\HideDesktopIcons\NewStartPanel.

So after this, where does all your deleted stuff go? To the Recycle Bin, of course! You've just done away with the icon from your desktop. To delete something from the Recycle Bin, delete it from C:\Recycled or C:\Recycler (the name depends on the file system).

The 'Copy To...' And 'Move To...' Context Options


To add the 'Copy to...' and 'Move to...' context menu options, create the following Registry keys:

HKEY_CLASSES_ROOT\AllFilesystemObjects\shell\Copy To
HKEY_CLASSES_ROOT\AllFilesystemObjects\shell\Move To
For 'Copy To', set the value to "{C2FBB630-2971-11d1-A18C-00C04FD75D13}", and for 'Move To', set the value to "{C2FBB631-2971-11d1-A18C-00C04FD75D13}". Henceforth, when you right-click on a file or folder, above the 'Send To' option, you'll see the two new options—"Copy To Folder" and "Move To Folder".

Using this, you can copy or move files or directories to other folders.

Add The Administrator To The Welcome Screen

Open the Registry Editor and go to HKEY_LOCAL_MACHINE\SOFTWARE\Microsoft\Windows NT\CurrentVersion\Winlogon\SpecialAccounts\UserList\ Here, create a new DWORD value. Name the new value 'Administrator'. Double-click this new value and enter '1' as Value Data. The new



An 'Administrator' icon in the Welcome Screen

user will be created on restart.

Get Rid Of Unwanted Items In "Open With..."

Ever wondered what help Internet Explorer could be when you want to watch a video file? But when you right-click any file, you're likely to see an option called 'Open With', which lists several available programs on your computer to open the file with. To clear up this list of unwanted items, or to remove useless associations like the one mentioned above, start the Registry Editor and navigate to HKEY_CURRENT_USER\Software\Microsoft\Windows\CurrentVersion\Explorer\FileExts Under this, find the extension you wish to edit