

This time Home is shown in the bold. When we click on the Screen1 link, the view changes and router replaces the contents of HomeComponent with Screen1Component.

Notice also Screen1 is highlighted as bold in the above screenshot.

Above example has one more component PageNotFound. Its activated when none of the url matches to defined routes.

Router State

After the culmination of each successful navigation lifecycle, a tree of ActivatedRoute objects is built by the router, that make up the current state of the router. The current RouterState can be accessed from anywhere in our application using the Router service and the routerState property.

Each ActivatedRoute in the RouterState does provide methods to get information we may need from parent, child and sibling routes by traversing up and down the route tree .

Route parameters

Above example does not passes any data between components but in real world a component may needs some kind of input data. It controls the part of business application which displays information to user or takes some action depending upon the current state. The Angular router can pass data to component in form of URL segments or query parameters, We call this route parameters.

We could have two types of route parameters:

1. Required router parameter

In the next example, a parameter is passed as a URL segment, the :id instructs router to match the text after /user/** and extract it into separate variable named "id". We can have as much path segments as we need.

- [{
- path: 'user/:id',
- component: UserDetailsComponent
- }]

This example matches URL such as <http://ex.com/user/1>, <http://ex.com/user/jack>. Extracted values are stored into variable as Javascript string.

We can specify the routerLink as,

- <a [routerLink]="['/users', 1]">Jack