




Figure 3: Image showing Batch Size

- **initial_epoch:** This indicates the epoch from which the model has to start training. It is quite useful for resuming a previous training run.
- **steps_per_epoch:** They indicate the total number of steps or the batches of samples before finishing one epoch and starting the next epoch. When using input tensors such as TensorFlow data tensors, the default steps_per_epoch is equal to the number of samples in the dataset divided by the batch size.
- **Verbose:** This specifies the verbosity mode depending on the argument (0, 1 or 2) specified. 0 means silent, one means progress bar, and 2 means one line per epoch verbosity.
- **validation_split:** It determines the fraction of the training data that is to be used as validation data. It takes the input as a floating point between 0 and 1. The model then sets apart this fraction of the training data and evaluates the loss and any model metrics on only this data at the end of each epoch. The validation data is selected from the end samples in the x and y data that is provided.
- **validation_data:** This takes input in the form of the tuple (x_val, y_val) or tuple (x_val, y_val, val_sample_weights) on which the model has to evaluate the loss and model metrics at the end of each epoch. The model is not trained on this data. Using this parameter will override validation_split.
- **Shuffle:** It is a Boolean type parameter that specifies whether to shuffle the training data before each epoch or not. In the case of HDF5 data,