


- Running Windows app through GUI

If you have worked on any IDE, running an application through GUI is similar to that. It will emulate the Windows file manager' environment and you can browse files through it. Navigate to the .exe file and open it to execute. You can ensure that it runs from WINE with a right click on the file, and then navigating to the "open with" option to look for "Wine Windows Program Loader."



Running a Windows application from WINE.

How to configure WINE

This section will help you learn about WINE prefixes, configuration, and how to configure using GUI.

- **WINE Prefixes**

It is a directory found beneath `$HOME/.wine`. This directory consists of configurations, which you can use to alter the Windows environment according to the need of the applications. After the very first installation, WINE will create certain default prefixes at the said directory.

1. `.update-timestamp`: Used to determine expiration date of a prefix, it contains `file/usr/share/wine/wine.inf` file's last modified date.
2. `dosdevices/`: Contains mapping details of Windows and FreeBSD resources. After a fresh installation, it will contain the following information: