

1. Start PC with Advanced Startup Options. To get access to Advanced Startup Options, keep the shift key pressed and then restart the computer. The screen should turn Blue and give you a set of options of which Advanced Startup Options should be one.
2. Click on Troubleshoot.
3. Click on Advanced options.
4. Click on Command Prompt.
5. When you start the device in Command Prompt, it will go to X:\Windows\System32. As a result, you must now navigate to the drive letter where Windows is installed. Although the operating system is installed on the C: disc, the drive letter may change when you boot your machine into recovery mode. In most cases, though, the drive letter is D:. As a result, perform the following command and press Enter to enter the right drive where Windows 10 is installed.

```
d:\
```

6. You now need to check if you are in the correct directory by checking the contents of the directory. Type the 'dir' command to confirm you are in the correct drive to restore the Registry and press Enter.

```
dir
```

7. If you see the Windows folder, you're on the right drive letter. If not, go back to step 5 and attempt a different drive letter.
8. To go into the System32 folder, type the following command and press Enter.

```
cd d:\windows\system32
```

Replace D with the relevant drive letter for your circumstance in the command.

9. To create a folder for temporary backup files on the config folder, which also happens to keep a copy of the Registry, type the following command and press Enter.

```
mkdir configBak
```

10. To create a temporary backup of the files in the config folder, type the following command and press Enter

```
copy config configBak
```

11. To travel into the RegBack, which stores a backup of the Registry, use the following command and hit Enter. Please remember, this only works until Windows 10 version 1803. If you are running a Windows older than that, you must create the backups manually or use a restore point.

```
cd config\RegBack
```