

INTERNET EXPLORER 7



IE7, at first look, is decent. You'd expect it to be perfect, what with its having been released so late (two years late, in our opinion). And it's not. The zoom feature has some problems—certain zoom and/or text size levels make some text disappear altogether; favicons (the icons associated with Web pages, which appear next to the site name) sometimes don't load, and so on. But on the whole, it's decent: there's tabbed browsing (finally), an easy way to add feeds and organise Favorites, a Quick Tab feature that shows you thumbnails of open tabs in the full window so you can switch to one or close some, and more.



Why's The File Menu There?

You might want to bring the File and other menus back where they "belong," that is, at the top. (That's one funny decision on the developers' part). It's a Registry edit. First back up the Registry, then navigate to HKEY_CURRENT_USER\Software\Microsoft\Internet Explorer\Toolbar\WebBrowser. Right-click in an empty area of the right pane, then select **New > DWORD**. Give it the name "ITBar7Position" (without the quotes). Double-click the newly-created value to give it a value of 1. Re-opening IE7 should make the change visible.



Setting A Wallpaper

One issue with IE7 is that in some cases, you might be trying to set an image as a wallpaper, and the option "Set as Background" might be greyed out. If that's the case, you'll need to do a Registry edit. First back up the Registry, then navigate to HKEY_CURRENT_USER\Software\Microsoft\Windows\CurrentVersion\Policies

\ActiveDesktop
Locate the entry called
NoChangingWallpaper, and change
that DWORD value to 0.



Multiple Homepages

Instead of just one homepage, you can have multiple homepages in IE7. When you're at a page that you want to add to your homepage list, click the down arrow next to the homepage icon. You'll be asked whether you want to set the page as your only homepage or add it to your "list of homepages" (still sounds funny to us). It so happens that you can also manage this from Internet Options.



Adding Feeds And Engines

Adding a feed or search engine couldn't be easier. When IE7 detects that a page has a feed on it, the feed button will light up (get coloured). Just click the down arrow next to it and it's clear from there on what to do. Now, press the Favorites button at any time to see a list of Favorites and Feeds as well as History. Right-click a feed and select Properties: you'll be able to select how often to update it, and other things.

To add a search engine, click the down arrow next to the search field. You'll get a Microsoft page that gives you directions on what to do to add an engine!



A list of common tasks and how to get them done quickly

- ❑ To disable all add-ons, Run "iexplore.exe -extoff".
- ❑ To turn on AutoComplete so that site addresses will be automatically filled in when you begin to type them, go to **Tools > Internet Options > Advanced > Use inline AutoComplete**.
- ❑ To change how tabs work, go to **Tools > Internet Options > General tab**. Under Tabs, click Settings.
- ❑ To display the Menu Bar permanently at the top of the screen, go to **Tools > Menu Bar**.
- ❑ To delete cookies, passwords, form data, history, and temporary Internet files, go to **Tools > Delete Browsing History**.
- ❑ To find and install add-ons, go to **Tools > Manage Add-ons > Find More Add-ons**.
- ❑ To print only part of a page, select the part, press [Ctrl] + [P], click Selection, then click Print.

Internet Explorer 7 Keyboard Shortcuts

Open a link in a new tab in the background	[Ctrl] + Click (or just middle-click)
Open a link in a new tab in the foreground	[Ctrl] + [Shift] + Click
Open a new tab in the foreground	[Ctrl] + [T]
Switch between tabs	[Ctrl] + [Tab] (forward) OR [Ctrl] + [Shift] + [Tab] (backward)
Close current tab (closes current window when there are no open tabs)	[Ctrl] + [W] OR [Ctrl] + [F4]
Open a new tab in the foreground from the address bar	[Alt] + [Enter]
Switch to the n th tab (n can be 1 to 8)	[Ctrl] + [n]
Switch to the last tab	[Ctrl] + [9]
Close all other tabs	[Ctrl] + [Alt] + [F4]
Open quick tab view	[Ctrl] + [Q]
View list of open tabs	[Ctrl] + [Shift] + [Q]
Increase zoom (+10%)	[Ctrl] + [+]
Decrease zoom (-10%)	[Ctrl] + [-]
Original zoom	[Ctrl] + [0] OR [Ctrl] + [*]
Go to the Toolbar search box	[Ctrl] + [E]
Bring down the search provider menu	[Ctrl] + [Down Arrow]
Go to home page	[Alt] + [Home]
Go backward a page	[Alt] + [Left Arrow]
Go forward a page	[Alt] + [Right Arrow]
Refresh the page and the cache	[Ctrl] + [F5]
Stop loading page	[Esc]
Open Favorites	[Ctrl] + [I]
Open Favorites in pinned mode	[Ctrl] + [Shift] + [I]
Organise Favorites	[Ctrl] + [B]
Add current page to Favorites	[Ctrl] + [D]
Open Feeds	[Ctrl] + [J]
Open Feeds in pinned mode	[Ctrl] + [Shift] + [J]
Open History	[Ctrl] + [H]
Open History in pinned mode	[Ctrl] + [Shift] + [H]
Select the Address Bar	[Alt] + [D]
View list of previously-typed addresses	[F4]
View list of search providers	[Ctrl] + [Down Arrow]