

enable it. To enable Chkdsk upon booting your PC, at a command prompt, use one of the following commands to enable or disable disk checking at startup:

chkntfs /D

(Default; this will check all volumes upon bootup when Windows is shut down improperly.)

chkntfs /C [volume]

(This will instruct Chkdsk to check only the volume you specify, which in this case is the [volume] variable. Replace it with the drive you want to be scanned, for example, **chkntfs /C E:**. You can then add more volumes to be checked by re-entering the command with the drive letter of your choice.

chkntfs /X [volume]

This will exclude a drive from being checked by check disk. Replace [volume] with the letter of the drive you don't want to be scanned. You can enter this command multiple times with different drive letters to exclude them from being checked.

the /D switch will set all options to default thus checking all drives following an improper shutdown

Reading, Writing, And NTFS

Q How do I create a bootable CD that will allow me to read from and write to NTFS partitions?

Nilesh Pawar

A You can use BartPE to create a bootable disc from your original Windows XP / 2003 CDs that will read from and write onto NTFS partitions. Get BartPE from www.nu2.nu/pebuilder, start it, and make it search for the source install files by clicking on Source and then on Search.

Your Windows CD should be in the CD-ROM drive when you're searching. Then select to create an ISO file. After the ISO file is created, you can burn it on an empty CD using a CD recording software like Nero.

Seeing Double

Q I am running Windows XP on an AMD 3000+ (939), MSI RS480M2 IL motherboard, 512 MB RAM, and an 80 GB hard disk. I have installed the graphics drivers that accompany the motherboard (display driver version 8.071 and control panel version 6.14). My problem is, I've connected a TV to the composite-out of the motherboard, and the system shows the TV as connected, but I am not able to get a display on the monitor and the TV at the same time (what the manual refers to as cloning of displays). I've tried using the latest Catalyst drivers but the problem persists. Please help. Also, how can I use the Extended Displays option?

Abhishek Mathur

A Try the following steps to troubleshoot your problem:

- ❑ In the BIOS, go to Advanced Chipset Features and change the TV standard option. Try all the options if you are unsure of which standard to use.
- ❑ Again in the BIOS, under Advanced Chipset Features, set the Video Display Devices option to "CRT force, TV force". This will force the computer to also use the S-video connector.

❑ The cable you're using might be faulty; try a different one.

The Extended Display feature, called SurroundView in ATI's case, will allow you to work across multiple displays, allowing you to spread your windows between them. You will need an additional video card for using your second display; look in the manual for a list of supported display cards for using the Expanded Displays feature. After you have a video card in addition to your onboard video, you will also need to enable onboard graphics in the BIOS. Do so by going to the BIOS, and in Advanced Chipset Features, set the internal video mode to UMA. Move further down to find an option called "UMA frame buffer size"; change this to at least 64 MB. Next, move back to the main BIOS screen and set "Init Display first" to PCI-E, enable the SurroundView option just a notch below, and restart your computer after saving the changes. You can then use SurroundView by going to the Settings tab in the display properties in Control Panel.

A Bouquet Of Questions!

Q I have Fedora Core 4 installed. The problem is that I can't mount other drives in it. I have seven drives; Fedora is installed on drive F. Drives C, D, and E are on the first hard disk (40 GB, FAT32), while the other three drives, I, J, and K are on the second hard disk (80 GB, all NTFS).

I've read about commands for mounting drives in other Linux editions, but the problem is that I couldn't find where exactly to enter those specific commands.

In Windows XP SP2, I've got Winamp 2.91. The problem here is that it doesn't save the song it was playing before being closed. That is, it starts playing from the very first song of the playlist. On enabling the enqueue option as the default, it remembers the song but copies the playlist, so I get the same playlist twice. What can I do?

I couldn't convert my E drive to NTFS. It gives an error and says I should run checkdisk. But this doesn't solve the problem.

Finally, could I run *Max Payne* on Windows XP though it is mentioned in the Readme that the game is not thoroughly checked on XP? It crashes after a stage completes and when the next one loads. Changing compatibility mode doesn't help!

Amit Kumar

A ❑ For mounting your drives in Fedora Core 4, just open a command line terminal and type in the commands you've already read about.

- ❑ It's not possible in this version of Winamp to remember the last played song. There happen to be software like Neutrius which automatically play the last song upon starting.
- ❑ Make sure you use the /F switch for fixing when using chkdsk; the syntax would be **chkdsk E: /F**
- ❑ *Max Payne* does not officially support Windows XP. However, you can try to improve things by setting the compatibility mode to Windows 2000 or upgrading *Max Payne* to the latest version (1.5). ■