

My traceroute [v0.72] Tue Jun 19 10:17:46 2007

Host	Loss%	Latency	Seq	Stdev	Min	Max	Stdev
1. squid.jde.co.in	0.0%	0.3	0.4	0.2	0.0	0.6	0.1
2. 203.101.92.49	0.0%	238.3	67.0	0.8	238.3	70.2	0.2
3. 61.95.151.29	0.0%	233.3	78.6	14.6	233.3	64.2	0.4
4. 59.145.255.44	0.0%	251.2	73.3	22.0	251.2	72.0	0.4
5. 59.145.7.58	11.1%	368.2	133.5	48.2	368.2	301.4	0.4
6. 202.56.223.13	0.0%	297.5	99.7	44.1	297.5	79.4	0.4
7. 1281-p8-3.uk.lon1.eu.bt.net	0.0%	367.7	298.1	258.4	367.7	36.6	0.4
8. 106-49-211-38.eu.bt.net	0.0%	461.8	358.1	318.4	461.8	47.4	0.4
9. so-0-0-8.dub09.ip.tiscali.net	0.0%	480.6	381.5	311.6	510.3	74.3	0.4
10. yahoo-overture-gw2.dub09.ip.tiscali.net	0.0%	497.9	371.8	312.0	497.9	68.3	0.4
11. ge-1-2-bas-b2.ird.yahoo.com	0.0%	511.8	369.9	310.9	511.8	71.9	0.4
ge-1-4-bas-b2.ird.yahoo.com							
ge-1-4-bas-b1.ird.yahoo.com							
ge-1-2-bas-b1.ird.yahoo.com							
12. 71.us.www.vip.ird.yahoo.com	0.0%	551.7	388.3	307.0	551.7	76.0	0.4

mtr—a feature-packed traceroute application

Applications > System Tools > Terminal. Enter mtr followed by an IP or name of the remote machine, for example, mtr www.thinkdigit.com.

Mounting Windows Shares

Let's face it—too many people use Windows, so you're going to have to access Windows network shares some time or the other. Samba is what Linux uses to host shares and access remote ones. To do this, go to Applications > System Tools > Terminal. Create a location where you want to mount the network share by typing in mkdir /mnt/netshare, where "netshare" can be replaced by the name for the mount. Then type in mount -t cifs //MACHINEIP/SHARENAME /mnt/netshare. Press [Enter], and you might be asked for a password. The mount -smbsfs should work, but in Fedora, you need to use the -cifs parameter instead. Adding the -o username=myusername,password=mypassword set of parameters to the mount command authenticates password-protected shares. This parameter needs to be added between the mount command and the share location. (CIFS is short for Common Internet File System.)

To have this network share auto-mounted on bootup, go to Applications > Accessories > Text Editor. Open /etc/fstab. At the bottom of this text file, make an entry: //MACHINEIP/SHARENAME /mnt/YOURMOUNTLOCATION cifs password=yourpassword 0 0

Accessing NTFS Partitions

Just like Windows shares will have to be accessed through Linux at some point or the other, you will require access to Windows' NTFS file system too to move files around. Accessing NTFS partitions in Fedora or other RPM-based distributions can be done using the ntfsmount command. Start a terminal by going to Applications > System Tools > Terminal. Create a location to mount the NTFS partition, for example, mkdir /mnt/ntfs. Next, type in ntfsmount /dev/NTFSpartition /mnt/ntfs. This will mount the NTFS partition to the /mnt/ntfs mount point, and you


will be able to read and write from and to the partition.

You can have this NTFS partition auto-mounted on bootup using steps similar to those you used for auto-mounting network shares. Open the /etc/fstab file in a text editor and add the following entry at the end of the file:

```
/dev/NTFSpartition /mnt/ntfs
ntfs-fuse
```

Installing Java

Fedora doesn't come with Java installed; you're going to have to download it and install it yourself. Download the latest RPM of the Java



The Java Environment installed and running on Linux

Runtime or Development Kit from <http://java.sun.com/javase/downloads/index.jsp>. Next, go to Applications > System Tools > Terminal. Navigate to the location of the downloaded file. If you downloaded the self-extracting .bin (like we did), run it using ./filename.

Mounting ISO Images

ISO images are disc images of CDs or DVDs. In places where you need to access data on the images when there is no DVD drive available, you can mount the ISO as a filesystem in the same way Windows users would using software like Alcohol 120%.

First create a new folder where you'll be mounting the ISO. Go to Applications > System Tools > Terminal. Navigate to the location of the ISO image. Use the command mount -o loop -t iso9660 ISONAME.iso /location.

Setting Up A Network Proxy

For machines that are behind proxies, it doesn't allow vital programs like yum to access repositories over the Internet. To enable a network proxy, go to System > Internet and Network > Network Proxy. Enter the details for

the different protocols and click Close. You can enter an Automatic Proxy Configuration address so the program can pick up all the proxy details from there. This network proxy configuration should work for all applications supporting proxy servers.

Disable Loading Of Modules

After a period of time, you'll end up having loads of processes starting on bootup. There are many which most of us don't really require. You can disable these to save loads of memory while also reducing bootup time.

Go to System > Administration > Services. Under the Background Services tab, uncheck the boxes for the services you do not want loaded at startup. Click Save to close the window. You can also start and shut down the services from this window: click on a service and click the Start, Stop, or Restart button.

Installing And Using Wine

Wine stands for "Windows Emulator", and can run quite a lot of Windows applications on Linux. Wine doesn't come with Fedora, so you need to install it using yum. Start a terminal and type in yum install wine. Once it's installed, use the File Browser to browse through your Windows partition or to the location of the Windows binaries if you already know where they are. Right-click on the executable and click on Open with Wine Windows Emulator. You can also alter the Wine settings by going to Applications > Wine > Wine Configuration. Here you can choose which version of Windows you want to mimic, and set paths of important Windows folders.

Extract RPM Files To A Particular Folder

RPM is a packet manager was developed by Red Hat Linux. You can extract the contents of RPM files into a directory of your choice than just installing it. Start a terminal by going to Applications > System Tools > Terminal. Navigate to the folder to where you want to extract the RPM file. Type in rpm2cpio rpmfile.rpm | cpio -idmv, and the RPM will be extracted.

Let Yum Auto-update Fedora

Updating Fedora can be done by a single command. yum will connect to the Internet, and download and install all the updates. Go to Applications > System Tools > Terminal. If you are already root, type in yum update. Use this command carefully: users with limited download connections could have a problem, since there can be quite a few updates. ☒