

► **Problem:** Auto-disconnect doesn't work, or the settings change.
Solution: If the settings change, visit <http://support.microsoft.com/default.aspx?scid=kb;EN-US;Q230142>

If auto disconnect doesn't work, go to the advanced options of your dial up settings: in Internet Explorer, go to Tools > Internet options > Connections > Dial-up settings > Advanced dial-up settings, and turn on the option to "disconnect if connection no longer required."

Also see these links:

<http://support.microsoft.com/support/kb/articles/q153/9/65.asp>

<http://support.microsoft.com/support/kb/articles/q180/9/48.asp>

<http://support.microsoft.com/support/kb/articles/q193/5/55.asp>

<http://support.microsoft.com/support/kb/articles/Q256/3/02.ASP>

If that doesn't work, open the Registry Editor, and navigate to HKEY_CURRENT_USER\RemoteAccess\Profile\<Connection>

Now look at the following DWORDS:

EnableExitDisconnect

EnableAutodisconnect

If either one has the data of 00 00 00 00, right-click the value and select Modify. Change the data to 01 00 00 00.

Also check this registry key: HKEY_CURRENT_USER\Software\Microsoft\Windows\CurrentVersion\Internet Settings. Look at the DWORD: EnableAutodisconnect. If this value has the data of 00 00 00 00, change it to 01 00 00 00. Reboot your computer.

► **Problem:** Web pages take too long to get displayed.

Cause: Your browser cache may be full.

Comments: Your computer stores temporary copies of the sites you visit on your hard drive, which helps each site open much faster when you visit it again. This set of stored files is called a cache. If the cache gets too big, it may take a long time to display a Web page in your browser.

Solution: You can empty your cache in Internet Explorer by selecting Tools > Internet Options, then under the General tab, delete the files and cookies.