

After] using some text editor. Check the difference between the entries in the two files. No, we are not suggesting you to manually compare every line.

#diff Before After + [Enter]

The output of the above command is the extra module that got activated due to insertion of Flash drive. Most likely the module is */lib/modules/2.4.20-8/kernel/drivers/scsi/sd_mod.o*

Therefore, the Flash drive can be mounted on your system by issuing the mount command:

#mkdir /mnt/flash + [Enter]

#mount /dev/sda1 /mnt/flash + [Enter]

The content of the Flash drive is accessible from the */mnt/flash* folder.

/ETC/FSTAB

The file '*fstab*' located under the folder */etc* is the back bone of the mount command. Mount reads */etc/fstab* and mounts the partitions or devices listed under it. A typical '*fstab*' file would read similar to the one below:

This file is edited by fstab-sync—see 'man fstab-sync' for details

```

LABEL=/          /          ext3          defaults          1 1
LABEL=/anup      /anup      ext3          defaults          1 2
LABEL=/boot      /boot      ext3          defaults          1 2
/dev/devpts      /dev/pts   devpts       gid=5,mode=620   0 0
/dev/shm         /dev/shm   tmpfs        defaults          0 0
LABEL=/home      /home      ext3          defaults          1 2
/dev/proc        /proc      proc         defaults          0 0
/dev/sys         /sys       sysfs        defaults          0 0
LABEL=/tmp       /tmp       ext3          defaults          1 2
LABEL=/usr       /usr       ext3          defaults          1 2
LABEL=/var       /var       ext3          defaults          1 2
/dev/hdc         /media/cdrecorder  auto
pamconsole,exec ,noauto,managed 0 0

```