



Set the “(Default)” value here to the command that should be executed when the folder is clicked. In this case, it would be “explorer /root, c:\Digit Archive”

Create another set of sub-keys called

`HKEY_CLASSES_ROOT\CLSID\{FD4DF9E0-E3DE-11CE-BFCF-ABCD1DE12345}\ShellEx\PropertySheetHandlers\{FD4DF9E0-E3DE-11CE-BFCF-ABCD1DE12345}`

Then create another sub-key called

`HKEY_CLASSES_ROOT\CLSID\{FD4DF9E0-E3DE-11CE-BFCF-ABCD1DE12345}\ShellFolder`

Under this key, create a new Binary Value called **Attributes** with the value “00 00 00 00”.

To put the folder on the Desktop, add the following key:  
`HLM\SOFTWARE\Microsoft\Windows\CurrentVersion\Explorer\Desktop\NameSpace\{FD4DF9E0-E3DE-11CE-BFCF-ABCD1DE12345}`

To place the folder in My Computer, add the following key: