

'displayPage' with a parameter of '0'. No matter how many pages there are, 0 will always be the first page.

- Go to the last page: this becomes a little tricky, as we don't know which page will be the last till we read the data. What we will do instead is, extend the 'displayPage' function to support a parameter of '-1' which will always correspond to the last page. You can choose to use infinity, but that would take rather long to type!
- Go to the previous page and next page: We will create a new function for this, and also add a variable which stores the current page number. The function needs to account for the fact that the user may click on the next page button when they are on the last page already, or click on the previous page button when they are in fact on the first page. This new function will take a parameter of 1 or -1 to signify the direction in which to go.

Take a look at the updated 'displayPage' and new 'gotoPage' functions.

```
var currentPage = 0;

function displayPage(pagenum){

    if (pagenum == -1)
        pagenum = noOfPages - 1;

    currentPage = pagenum;
    startItem = pagenum * itemsPerPage;
    endItem = startItem + itemsPerPage;
    while (movieTable.rows.length > 1)
        movieTable.deleteRow(1);
    for (i = startItem; i < endItem; i++) {
        newrow = movieTable.insertRow(-1);
        newrow.insertCell(-1).innerHTML =
data[i].getElementsByTagName('rank')[0].text-
Content;
        newrow.insertCell(-1).innerHTML =
data[i].getElementsByTagName('name')[0].text-
Content;
        newrow.insertCell(-1).innerHTML
= data[i].getElementsByTagName('earning')[0].
```