

```

enabled          true
state            online
next_state       none
state_time       Thu Jan 14 16:04:18 2010
logfile          /var/svc/log/network-http:apache22.log
restarter        svc:/system/svc/restarter:default
contract_id      70
dependency       require_all/error    svc:/milestone/
network:default  (online)
dependency       require_all/none     svc:/system/filesystem/
local:default    (online)
dependency       optional_all/error   svc:/system/filesystem/
autofs:default   (online)

```

For more information check the main pages of `svcs` and `svcadm`.

3.7 Tips on troubleshooting an OpenSolaris startup

You can switch from the default graphical boot screen to the text boot screen. The ability to switch to the text boot screen can be useful if you suspect that the system startup process is not proceeding normally. The text screen might contain informational messages or a request for user input. Switching to the text boot screen has no impact on the boot sequence, other than how the information is displayed on the screen. Initialization of the operating system continues and completes as normal. To switch to a text boot, press any key a few seconds after the graphical boot screen appears, and the progress bar starts.

3.7.1 Boot modes

If the graphics card on your system is not supported, the system boots in console mode when you insert the Live CD and attempt to use the GUI installer. Should you encounter this problem, use the following procedure, which describes how to perform an installation by logging in to another system and running the GUI installer remotely.

If Your System Boots in Console Mode, you can install from the Live CD. To do this, you'll need two networked systems: the system on which the OpenSolaris Live CD was booted (target system) and a remote system from which the installation will be performed. Both systems must have network access. It is not required that the two systems be on the same subnet. However, the target system must be reachable from the remote system. Also, the remote system must be running an operating system that supports a