

1. Boot the system in single-user mode.
 - a. When the boot sequence starts, and the GRUB menu is displayed, type **e** to display the GRUB edit menu.
 - b. Using the up or down arrow keys, select the kernel\$ line, then type **e** to edit that entry.
 - c. Type **-s** at the end of the kernel\$ entry.
 - d. Press **[Enter]** to go back to the previous screen.
 - e. To boot the system in single-user mode, type **b**.
2. When prompted, type an account name. The account name can be root, or any other privileged account, such as **jack** on the Live CD, or an account that you created during the installation.
3. Type the root password.

After the system has booted, depending on your particular situation, you can do any of the following:

Display the existing user accounts and roles:

```
-bash-3.2# cat /etc/user_attr
```

Delete a user account:

```
-bash-3.2# userdel username
```

Create a new user account:

```
-bash-3.2# useradd username
```

- a. Assign a password for the user name.

```
-bash-3.2# passwd username
```

You will need to type the password twice.

- b. Assign the root role to that user.

```
-bash-3.2# usermod R root username
```

4. To return to the installed system, type **exit**.

Digit Subscription

Subscribe to the Digit developer newsletter at www.thinkdigit.com/newsletter

3.7.3 How to add the zfsnap role to the default user account

The default user account that is created when you install the OpenSolaris operating system includes the Primary Administrator profile. This account effectively has the same privileges as the root user. However, the default user account does not have the zfsnap role assigned to it, which is required to change Time Slider behaviour in the GNOME file browser. Before you can change Time Slider behaviour in the file browser, you must assign the zfsnap role to your default user account.

1. Choose **System > Administration > Users and Groups**.
2. Select your user account, then click the Properties button. The Settings