

window for your user account is displayed.

3. To display the roles that are assigned to your user account, click the User Roles tab.
4. Place a check mark in the check box next to zfssnap, then click **Ok** to return to the Users and Groups window.
5. Save the settings.
6. To verify the role was assigned, open a terminal window and type:

```
$ roles  
root, zfssnap
```

3.8 Troubleshooting Device Drivers

If a device driver is missing, a peripheral device may not work properly. Therefore it is important to install drivers for the peripheral devices that you want to use.

3.8.1 Installing a driver package from the IPS repository

Run the Device Driver Utility. Choose **Applications > System Tools > Device Driver Utility**. If a highlighted entry indicates a driver is available in the IPS repository (driver available), the tool can download and install the driver package for you. Make sure your system has Internet Access. Right-click the highlighted entry. Select the **Install Driver** option from the popup that is displayed. Alternately, you can install all missing drivers by clicking the **Install All Drivers** button.

3.8.2 Install a driver package not within the IPS repository

Run the Device Driver Utility. Choose **Applications > System Tools > Device Driver Utility**. If a highlighted entry indicates a third-party driver is available for that device (third-party), then the tool can display the URL to the recommended driver. Right-click the highlighted entry. Select the **Show Details** option from the popup that is displayed. At the top of the Details window, a URL to the recommended driver is displayed. To install the driver, follow the installation instructions that are included with the driver package.

In most cases, the driver is installed by copying the driver's binary file and its configuration file, if one exists, to the correct location on your system.

64-bit x86 drivers – Copy the driver to the `/kernel/drv/amd64/` directory. 32-bit x86 drivers – Copy the driver to the `/kernel/drv/` directory. 

