

syntax:

```
sudo deluser username
```

Just deleting an account will not remove their respective home folder. It's up to you whether or not you wish to delete the folder manually or keep it according to your desired retention policies. Remember, any user added later on with the same UID/GID as the previous owner will now have access to this folder if you have not taken the necessary precautions.

You may want to change these UID/GID values to something more appropriate, such as the root account, and perhaps even relocate the folder to avoid future conflicts:

```
sudo chown -R root:root /home/username/  
sudo mkdir /home/archived_users/  
sudo mv /home/username /home/archived_users/
```

To temporarily lock or unlock a user account, use the following syntax, respectively:

```
sudo passwd -l username  
sudo passwd -u username
```

To add or delete a personalized group, use the following syntax, respectively:

```
sudo addgroup groupname  
sudo delgroup groupname
```

To add a user to a group, use the following syntax:

```
sudo adduser username groupname
```

Where is root?

Ubuntu developers made a conscientious decision to disable the administrative root account by default in all Ubuntu installations. This does not mean that the root account has been deleted or that it may not be accessed. It merely has been given a password that matches no possible encrypted value, and therefore, may not log in directly by itself.

Instead, users are encouraged to make use of a tool called **sudo** to carry out system administrative duties. **Sudo** allows an authorised user to temporarily elevate their privileges using their own password instead of having to know the password of the root account. This simple, yet, effective methodology provides accountability for all user actions, and gives the administrator granular control over which actions a user can perform with the said privileges.

If, for some reason, you wish to enable the root account, simply give it a password:

```
sudo passwd
```

Sudo will prompt you for your password, and then ask you to supply a new password for root as shown below:

```
[sudo] password for username: (enter your own password)  
Enter new UNIX password: (enter a new password for root)
```