


dragging it down and to the right. In the lower-right corner of Visual Studio, find the size and location information for controls. Set the size of the control to a width of 500 and a height of 400 by watching the size information as you resize the control.

2. In the Toolbox, click the Containers node to open it. Select the SplitContainer control and drag it onto the designer surface.

The SplitContainer is placed on the DemoCalculator control's designer surface.

3. In the Properties window, change the value of the Dock property to None.



Set various parameters

The SplitContainer control shrinks to its default size. Its size no longer follows the size of the DemoCalculator control.

4. Click the smart tag glyph () on the upper-right corner of the SplitContainer control. Click Dock in Parent Container to set the Dock property to Fill. The SplitContainer control docks to the DemoCalculator control's boundaries.

5. Click the vertical border between the panels and drag it to the right, so that most of the space is taken by the left panel. The SplitContainer divides the DemoCalculator control into two panels, with a movable border separating them. The panel on the left will hold the calculator buttons and display, and the panel on the right will show a record of the arithmetic operations performed by the user.

6. In the Properties window, change the value of the BorderStyle property to Fixed3D.

7. In the Toolbox, click the Common Controls node to open it. Select the ListView control and drag it into the right panel of the SplitContainer control.

8. Click the ListView control's smart tag glyph. In the smart tag panel, change the View setting to Details.

9. In the smart tag panel, click Edit Columns. The ColumnHeader Collection Editor dialog box opens.

10. In the ColumnHeader Collection Editor dialog box, click the Add button to add a column to the ListView control. Change the value of the column's Text property to History. Click OK to create the column.

11. In the smart tag panel, click Dock in Parent Container, and then click the smart tag glyph to close the smart tag panel.