




the effect of moving a joint to the skin around adjacent joints. Link Settings determine how the skin between joints behaves, such as the crease of an elbow.



Bulges can be accessed by using the Bulge sub-object, but there is also a floating Bulge Editor window that provides a graphical interface. Bulging is configured by animating the joint and setting bulge angles for each point. For the bulging of a bicep, for example, the elbow would be animated straight and at 90 degrees to create two bulge angles. Then using the Bulge Editor or the interactive tools in the viewport, the cross sections and control points are reshaped to create the desired bulge at each angle.

Control Point tools – Tools to draw, create, and delete control points.

Select and Translate – Tools to select, move, rotate, and scale control points.

Bulge profile – The profile of the bulge is displayed graphically.

Cross Section tools – Tools to create, delete, and adjust cross sections.

Bulge Angle tools – These buttons set, insert, and delete bulge angles from the pull-down list.

Bulge angle – The selected bulge angle. The bulge angle can be changed by pulling down the list.

Bulge angle parameters – Influence, Power, and Weight parameters, exactly the same as in the Bulge sub-object rollout.

Cross Section/Bulge Angle – Switches between Cross Section and Bulge Angle mode. 