

```

1 package com.thinkdigit.envy;
2 import android.app.Activity;
3 import android.os.Bundle;
4 publicclass StatusActivity extends Activity {
5 /** Called when the activity is first created. */
6 @Override
7 publicvoid onCreate(Bundle savedInstanceState) {
8 super.onCreate(savedInstanceState);
9 setContentView(R.layout.status);
10.}
11. }
```

Change `R.layout.main` on line 9 to `R.layout.status`.

Now, double-click on `status.xml` in `res/layout` folder. You'll see a screen with four components: a title at the top, which is the `TextView` widget; a text area to type the 140 character status update, where we use an `EditText` widget; a button at the bottom to update the status, using the `Button` widget; and a layout containing all these widgets aligned in vertical fashion. Here we're using `LinearLayout`. This view is the Graphical layout mode.

You can view the raw XML code by clicking on the `status.xml` tab at the bottom of this screen. This code was generated in the Eclipse graphical layout. ADT Eclipse plug-in provides this to help you work with Android-specific files. Replace the code in `status.xml` with the following code:

```

1 <?xml version="1.0" encoding="utf-8"?>
2 <!-- Main Layout of StatusActivity -->
3 <LinearLayout xmlns:android="http://schemas.android.com/apk/
res/android"
4 android:orientation="vertical"
5 android:layout_width="fill_parent"
6 android:layout_height="fill_parent"
7 >
8 <!-- Title text view -->
9 <TextView
10 android:layout_width="fill_parent"
11 android:layout_height="wrap_content"
12 android:gravity="center"
13 android:textSize="30sp"
14 android:layout_margin="10dp"
15 android:text="@string/titleStatus"
```